

ITEM OR TASK	GALILEO FORMAT	SABRE SYSTEM FORMAT
End item key	+	\$
Change key	▣	▣
Cross of Lorraine		¥
Sign in	SON/Z(sine) (passcode) SON/Z1234AB CODE1	SI*(sine) (passcode) SI*1234 CODING1
Sign out	SOF	SO*
Replay one entry	A previous format can be reentered with arrow up and enter	Alt + arrow up/down to use replay Use the ESC key to reset cursor to set the start of the format and then arrow to the end to enter.
Accumulated responses can be turned on/off	Only has the equivalent to "accumulated responses off"	Select the option/configuration if they like a "clearer" screen
Calculator and time functions		
Calculator - Add	XX(number)+(number) XX45+24	T▣ (number) ¥ (number) T▣45¥24
Calculator – Subtract	XX(number)-(number) XX100-4	T▣ (number)-(number) T▣100-4
Calculator - Multiply	XX(number)*(number) XX198*2	T▣ (number)*(number) T▣198*2
Display minimum connecting time	DCT	T*CT-JFK/AA
Display times in 24 hours	HMCT▣24/LT	HR24
Display times in 12 hours	HMCT▣12/LT	HR12
Display local time in a specific city	▣LT(city) ▣LTLAX	T*(city) T*LAX
Display information and Help		
Request help	/HELP	/HELP

ITEM OR TASK	GALILEO FORMAT	SABRE SYSTEM FORMAT
Scrolling and replay		
Move down	MD	MD
Move up	MU	MU
Move bottom	MB	MB
Move top	MT	MT
Move down 100 lines	MD100	MD100
Replay one entry	A previous format can be reentered with arrow up and enter	Alt + arrow up/down to use replay Use the ESC key to reset cursor to set the start of the format and then arrow to the end to enter.
Taxes		
Tax information by country name	FTAX-FRANCE	TXN*FRANCE
Tax information by country code	FTAX-GB	TXN*GB
Passenger facility charge (PFC) for airport code	FTAX*PFC-MIA	PXC*MIA
Queues		
Display queue count	QCA	QC/
Display queue count on specific queue	QCB/9	QC/9
Access general queue	Q/1	Q/G
Send PNR to queue	QEP/(number) QEB/44	QP/(number)/(prefatory instruction code) QP/44/5
List prefatory instruction codes	QPB*	QI*SYS
Exit queue	QX+I	QXI
Access urgent or supervisor queues	QCS (urgent queues)	Q/S (supervisor queue)
Add unable to reach remark	QUTC*(free text) QUTC*CALL AFTER 6P	QU-(free text) QU-CALL AFTER 1800
Add left message to call remark	QLMCB*(free text) QLMCB*CALL MARY	QL-(name) QL-MARY
Remove PNR from queue	QR	QR

Encode - Decode

TASK	GALILEO FORMAT	SABRE FORMAT
Encode airline name	.AE (carrier name) .AE IBERIA	W/-AL(carrier name) W/-ALIBERIA
Decode airline code	.AD (two letter airline code) .AD RG	W/*(carrier code) W/*RG
Encode airport or city name	.CE (city name) .CE ROCHESTER	W/-CC(city name) W/-CCROCHESTER
Decode airport or city code	.CD (airport code) .CD NYC	W/*(airport code) W/*NYC
Encode car company name	GC*12/CAR/(car company name) GC*12/CAR/HERTZ	W/-CR(car company name) W/-CRHERTZ
Decode car company code	GC*12/CAR/(car company code) GC*12/CAR/ZE	W/CR*(car company code) W/CR*ZE
Encode hotel company name	GC*11/HTL/(hotel company name) GC*11/HTL/SHERATON	W/-HL(hotel company name) W/-HLSHERATON
Decode hotel company code	GC*11/HTL(hotel company code) GC*11/HTL/SI	W/HL*(hotel company code) W/HL*SI

Request seats and display Seat Map

Display seat map by segment number	SM*S(segment number) SA*S4	4G(segment number)* 4G3* Note: the graphical seat map displays.
Request window seat	S.S(segment)/ W S.S1/W	4G(segment number)/ W 4G1/W
Assign specific seats	S.S(segment number)/(seat numbers) S.S3/10A	4G(segment number)/(seat numbers) 4G1/12A
Cancel seat	S.S(segment number)@ S.S5@	4GX(segment number)/(seat number) 4GX3/14A
Display seat assignments	*SD	*B